

Setting Adobe Acrobat (Pro) as your default program for .pdf files





Apps & features

Installing apps

Choose where you can get apps from. Installing only apps from the Store helps protect your PC and keep it running smoothly.

 \sim



Apps & features

Manage optional features

Manage app execution aliases

Search, sort, and filter by drive. If you would like to uninstall or move an app, select it from the list.



Sort by: Name 🗸 🛛 Filter by: All drives 🗸



Associate file types	with specific apps Default	арр	
.386 Virtual device driver	+ Scroll through the list until		
.3g2 3GPP2 Audio/Video		you see .pd	f
.3gp 3GPP Audio/Video		Windows Media Play	/er
.3gp2 3GPP2 Audio/Video		Windows Media Play	ver
.3gpp 3GPP Audio/Video		Windows Media Play	ver
.3mf 3D Object	(A	Print 3D	
.a A File	+	Choose a default	
.aac ADTS Audio		Windows Media Play	ver
.aaui Acrobat User Interface		Adobe Acrobat DC	
.ac3 AC3 File	Кеер	roove Music	
.accda Microsoft Access Add-in	scrolling	ccess	
	fault apps by	file type	
.pcb PCB File	+	Choose a default	If Adobe Acrobat is not listed as the default program for pdf
.pch PCH File	+	Choose a default	files, then click on the icon shown and
.pdb PDB File	+	Choose default	choose Adobe Acrobat
.pdf Adobe Acrobat Document	<u>ہ</u>	Adobe Acrobat DC	6
.pdfxml Adobe Acrobat Document	L	Adobe Acrobat DC	
.pds PDS File	+	Choose a default	• For a

• For assistance with this process, contact Kelly Case, Business Process Trainer, klcase@washoeschools.net

Adjusting Google Chrome to open .pdf files in Adobe



By default, Google Chrome opens a <u>PDF</u> file in the browser window instead of opening it with Adobe. To change how Google Chrome treats PDF files in the browser, follow the steps below.

- 1. Open the <u>Google Chrome</u> browser.
- 2. Click the icon in the top-right corner of the browser window.
- 3. Select **Settings** from the <u>drop-down menu</u> that appears.
- 4. On the Settings window, under *Privacy and security*, click the **Site Settings** option.
- 5. Scroll down the *Site Settings* screen to find and click the **PDF documents** option.
- 6. Next to Download PDF files instead of automatically opening them in Chrome, click the toggle switch to
 the On or Off position. Chrome opens a PDF in Adobe when the toggle switch is set to On and displays a PDF in the browser when set to Off.
- You may have to expand Additional Content Settings to see the prompt for **PDF documents**

 For assistance with this process, contact Kelly Case, Business Process Trainer, klcase@washoeschools.net



Adjusting Edge to open .pdf files in Adobe

Change the settings in Microsoft Edge. Step 1. click on the three dots ... in the top right corner of the browser Step 2. select "Settings" from the pull-down menu. Step 3. type PDF into the "search" box and scroll the right-hand window until you see the option "PDF Documents". Step 4. click on the "PDF Documents" to open the options: Step 5. click on the slider on the far-right to enable "Always download PDF files".

This changes the default option so that when you click on a PDF file, it now downloads it from the web and gives you the option to open with Adobe Reader (or Adobe Pro) first.

lways download PDF file			
ownload PDF files to your dev	e. If Microsoft Edge is your default PDF reader, PDF	files will open automatically without downloading.	
DF view settings			
pen PDFs to last viewed locat	n when you reopen files		

• For assistance with this process, contact Kelly Case, Business Process Trainer, klcase@washoeschools.net